



Artisan Technology Group is your source for quality new and certified-used/pre-owned equipment

- FAST SHIPPING AND DELIVERY
- TENS OF THOUSANDS OF IN-STOCK ITEMS
- EQUIPMENT DEMOS
- HUNDREDS OF MANUFACTURERS SUPPORTED
- LEASING/MONTHLY RENTALS
- ITAR CERTIFIED SECURE ASSET SOLUTIONS

SERVICE CENTER REPAIRS

Experienced engineers and technicians on staff at our full-service, in-house repair center

*InstraView*SM REMOTE INSPECTION

Remotely inspect equipment before purchasing with our interactive website at www.instraview.com ↗


WE BUY USED EQUIPMENT

Sell your excess, underutilized, and idle used equipment. We also offer credit for buy-backs and trade-ins. www.artisanng.com/WeBuyEquipment ↗

LOOKING FOR MORE INFORMATION?

Visit us on the web at www.artisanng.com ↗ for more information on price quotations, drivers, technical specifications, manuals, and documentation

Contact us: (888) 88-SOURCE | sales@artisanng.com | www.artisanng.com



Getting Results with HiQ™ Reader



January 1999 Edition
Part Number 322242A-01

Worldwide Technical Support and Product Information

www.natinst.com

National Instruments Corporate Headquarters

11500 North Mopac Expressway Austin, Texas 78759-3504 USA Tel: 512 794 0100

Worldwide Offices

Australia 03 9879 5166, Austria 0662 45 79 90 0, Belgium 02 757 00 20, Brazil 011 284 5011,
Canada (Ontario) 905 785 0085, Canada (Québec) 514 694 8521, Denmark 45 76 26 00, Finland 09 725 725 11,
France 0 1 48 14 24 24, Germany 089 741 31 30, Hong Kong 2645 3186, India 91805275406,
Israel 03 6120092, Italy 02 413091, Japan 03 5472 2970, Korea 02 596 7456, Mexico (D.F.) 5 280 7625,
Mexico (Monterrey) 8 357 7695, Netherlands 0348 433466, Norway 32 84 84 00, Singapore 2265886,
Spain (Madrid) 91 640 0085, Spain (Barcelona) 93 582 0251, Sweden 08 587 895 00,
Switzerland 056 200 51 51, Taiwan 02 2377 1200, United Kingdom 01635 523545

For further support information, see the *Technical Support Resources* appendix of this manual.

© Copyright 1999 National Instruments Corporation. All rights reserved.

Important Information

Warranty

The media on which you receive National Instruments software are warranted not to fail to execute programming instructions, due to defects in materials and workmanship, for a period of 90 days from date of shipment, as evidenced by receipts or other documentation. National Instruments will, at its option, repair or replace software media that do not execute programming instructions if National Instruments receives notice of such defects during the warranty period. National Instruments does not warrant that the operation of the software shall be uninterrupted or error free.

A Return Material Authorization (RMA) number must be obtained from the factory and clearly marked on the outside of the package before any equipment will be accepted for warranty work. National Instruments will pay the shipping costs of returning to the owner parts which are covered by warranty.

National Instruments believes that the information in this document is accurate. The document has been carefully reviewed for technical accuracy. In the event that technical or typographical errors exist, National Instruments reserves the right to make changes to subsequent editions of this document without prior notice to holders of this edition. The reader should consult National Instruments if errors are suspected. In no event shall National Instruments be liable for any damages arising out of or related to this document or the information contained in it.

EXCEPT AS SPECIFIED HEREIN, NATIONAL INSTRUMENTS MAKES NO WARRANTIES, EXPRESS OR IMPLIED, AND SPECIFICALLY DISCLAIMS ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. CUSTOMER'S RIGHT TO RECOVER DAMAGES CAUSED BY FAULT OR NEGLIGENCE ON THE PART OF NATIONAL INSTRUMENTS SHALL BE LIMITED TO THE AMOUNT THERETOFORE PAID BY THE CUSTOMER. NATIONAL INSTRUMENTS WILL NOT BE LIABLE FOR DAMAGES RESULTING FROM LOSS OF DATA, PROFITS, USE OF PRODUCTS, OR INCIDENTAL OR CONSEQUENTIAL DAMAGES, EVEN IF ADVISED OF THE POSSIBILITY THEREOF. This limitation of the liability of National Instruments will apply regardless of the form of action, whether in contract or tort, including negligence. Any action against National Instruments must be brought within one year after the cause of action accrues. National Instruments shall not be liable for any delay in performance due to causes beyond its reasonable control. The warranty provided herein does not cover damages, defects, malfunctions, or service failures caused by owner's failure to follow the National Instruments installation, operation, or maintenance instructions; owner's modification of the product; owner's abuse, misuse, or negligent acts; and power failure or surges, fire, flood, accident, actions of third parties, or other events outside reasonable control.

Copyright

Under the copyright laws, this publication may not be reproduced or transmitted in any form, electronic or mechanical, including photocopying, recording, storing in an information retrieval system, or translating, in whole or in part, without the prior written consent of National Instruments Corporation.

Trademarks


ComponentWorks™, HiQ™, HiQ-Script™, and natinst.com™ are trademarks of National Instruments Corporation. Product and company names mentioned herein are trademarks or trade names of their respective companies.

WARNING REGARDING MEDICAL AND CLINICAL USE OF NATIONAL INSTRUMENTS PRODUCTS

National Instruments products are not designed with components and testing for a level of reliability suitable for use in or in connection with surgical implants or as critical components in any life support systems whose failure to perform can reasonably be expected to cause significant injury to a human. Applications of National Instruments products involving medical or clinical treatment can create a potential for death or bodily injury caused by product failure, or by errors on the part of the user or application designer. Because each end-user system is customized and differs from National Instruments testing platforms and because a user or application designer may use National Instruments products in combination with other products in a manner not evaluated or contemplated by National Instruments, the user or application designer is ultimately responsible for verifying and validating the suitability of National Instruments products whenever National Instruments products are incorporated in a system or application, including, without limitation, the appropriate design, process and safety level of such system or application.

Conventions

The following conventions are used in this manual:

- » The » symbol leads you through nested menu items and dialog box options to a final action. The sequence **Help»HiQ Reader Help Topics** directs you to pull down the **Help** menu and select the **HiQ Reader Help Topics** item.
-  This icon denotes a note, which alerts you to important information.
- bold** Bold text denotes the names of menus and dialog box buttons or options.
- italic* Italic text denotes emphasis, a cross reference, or an introduction to a key concept.
- `monospace` Text in this font denotes text or characters that you should literally enter from the keyboard, sections of code, programming examples, and syntax examples. This font is also used for the proper names of disk drives, paths, directories, parameters, functions, variables, filenames and extensions, and for statements and comments taken from programs.

Contents

Chapter 1

Getting Started with HiQ Reader

About HiQ Reader	1-1
System Requirements	1-1
Installing HiQ Reader	1-2
Getting Started with HiQ Reader	1-3
Launching and Exiting HiQ Reader	1-3
Opening and Closing HiQ Reader Notebooks.....	1-3
Getting Help.....	1-5
HiQ Reader Online Help	1-5
Current Notebook	1-5

Chapter 2

Getting Results with HiQ Reader Notebooks

About HiQ Reader Notebooks	2-1
Notebook Objects	2-1
Scripts	2-2
Working with Multiple Windows.....	2-3
Interacting with a Notebook	2-3
Notebook Example: Expression Evaluator	2-3
Opening the Notebook.....	2-3
Entering Data and Running Scripts	2-4
More Reader Notebooks: Problem Solvers	2-5

Appendix A

Technical Support Resources

Glossary

Figures

Figure 1-1. HiQ Reader Environment	1-4
Figure 2-1. Expression Evaluator Problem Solving Scripts.....	2-2
Figure 2-2. Evaluating Expressions with the Expression Evaluator Notebook	2-4

1

Getting Started with HiQ Reader

This chapter introduces the HiQ Reader application, lists system requirements and installation instructions, and explains how to get started with HiQ Reader.

About HiQ Reader

The HiQ Reader enables you to interact with HiQ Professional Notebooks. You can open HiQ Professional Notebooks, run scripts, view the analysis and visualization results, and print and save the Notebooks. Refer to Chapter 2, *Getting Results with HiQ Reader Notebooks*, for information about Notebooks and extracting the data you need from it.



Note

HiQ Reader can open only Notebooks saved in HiQ Professional version.

The HiQ Reader is available for free from either your HiQ Professional CD or from the National Instruments Web site at www.natinst.com/hiq.

System Requirements

HiQ Reader requires the following minimum system configuration:

- Windows 95 or Windows 98/NT 4.0
- 486 CPU with coprocessor
- 8 MB RAM with Windows 95, 16 MB RAM with Windows 98/NT
- 256-color, 800 by 600 VGA display
- 20 MB free disk space

The following specifications are the recommended system configuration for HiQ Reader:

- Windows NT 4.0
- Pentium 90 or higher
- 16 MB RAM with Windows 95, 32 MB RAM with Windows 98/NT
- Accelerated True Color, 1024 by 768 display
- 20 MB free disk space

Installing HiQ Reader

HiQ Reader is part of the HiQ Professional edition. Use one of the following procedures to install the HiQ Reader application:

- If you purchased HiQ Professional:
 1. Insert the HiQ Professional CD in the CD-ROM drive of your computer.
 2. Follow the *Setup* instructions you see on your screen. Be sure to select the HiQ Reader option.
- If you do not have HiQ Professional:
 1. Visit the National Instruments Web site at www.natinst.com and follow the links to HiQ.
 2. Click **Download HiQ Reader** and save the file to your computer.
 3. Double click on the .EXE file that you downloaded.
 4. Follow the *Setup* instructions you see on your screen.

By default, the HiQ Reader installation program creates a new folder, C:\Program Files\National Instruments\HiQReader, that contains the following items:

- Program folder—HiQReader.exe, HiQ Reader help files, and related files
- Problem Solvers folder—Example Problem Solver Notebooks
- Readme.txt file—Late-breaking information about HiQ, known limitations, and corrections
- Manuals folder—PDF version of this manual

Getting Started with HiQ Reader

Launching and Exiting HiQ Reader

Use one of the following methods to launch HiQ Reader:

- Use the **Start** Button.
 1. Click on the Windows **Start** button and select the **Programs** menu.
 2. Select the **National Instruments HiQ** submenu.
 3. Click on **HiQ Reader**.
- Use Windows Explorer.
 1. Locate the HiQ Reader executable, `HiQReader.exe`, in Windows Explorer.
 2. Double click `HiQReader.exe`.


Use the following step to exit HiQ Reader:

1. Save the Notebook if you have made any changes to any objects.
2. Select **File»Exit**.

Opening and Closing HiQ Reader Notebooks

Use the following steps to open and close HiQ Reader Notebooks:

1. Launch HiQ Reader.
2. Select **File»Open**.
3. Navigate to the file you want to open, select the file, and press **Open**.
4. Interact with the Notebook. You can run scripts and print and save the Notebook. You cannot create new objects, delete objects, or modify the format of the Notebook. Refer to Chapter 2, [Getting Results with HiQ Reader Notebooks](#), for more information about Notebooks and interacting with them.



Note

HiQ Reader can open all Notebooks saved as HiQ Reader Notebooks (.HQR) and HiQ Notebooks saved in HiQ Professional. HiQ Professional Notebooks are saved with the same extension as those created in the base version of HiQ (.HIQ). HiQ Reader displays an error message if you try to open an Notebook that was not saved in HiQ Professional.

Figure 1-1 shows the Filtering Problem Solver Notebook, which you can find in the \Problem Solvers folder. This figure labels important parts of the HiQ Reader and some of the elements on the Notebook page. For more information about getting results with a Problem Solver, see *Notebook Example: Expression Evaluator* in Chapter 2, *Getting Results with HiQ Reader Notebooks*.




Figure 1-1. HiQ Reader Environment

- To close the Notebook, select **File»Close**.

Getting Help

HiQ Reader Online Help

HiQ Reader offers tooltips, context-sensitive help, and online help that you can access in the following ways.

- You can access the HiQ Reader online help by selecting **HiQ Reader Help Topics** from the **Help** menu. There you find information not available in this manual, such as complete function reference and answers to *How Do I...?* questions.
- Tooltips appear when you move the mouse cursor over a button in any toolbar. The text of the tooltip indicates the function of the button.
- A help topic appears in the status bar at the bottom of a HiQ Notebook as you move the mouse pointer over the menu items.
- You can click on the Help button, **?**, in other areas of the HiQ user interface, such as dialog boxes, to access context-sensitive help for the next item on which you click.



Note

Use the <F1> key to access context-sensitive help for a selected item or for an area where the cursor is located. For example, when your cursor is located in a script within the name of a HiQ built-in function, help for that function appears when you press <F1>.

Current Notebook

Notebook developers can create and distribute help for the Notebooks they create. Help files can have any of the formats in the following table:

File Extension	File Type	Description
.hlp, .cnt	WinHelp	Windows standard help file that looks and behaves similar to the HiQ Reader online help
.chm, .chh	HTML Help	Microsoft Compiled HTML Help
.htm, .html	Web page	HTML page that opens in your default Web browser
.doc	Word document	Microsoft Word document
.txt	Text file	Plain text file that opens in your default text editor

If you receive any files with these extensions with a HiQ Reader Notebook, place all files in the same directory. When the Notebook is open in the HiQ Reader, you can access the help by selecting **Help»Help for Current Notebook**.

Getting Results with HiQ Reader Notebooks

This chapter introduces the features of the HiQ Notebook interface and shows you how to interact with HiQ Reader Notebooks in HiQ Reader.

About HiQ Reader Notebooks

HiQ uses a notebook as the basic interface metaphor. The HiQ *Notebook* has features that you normally associate with a real engineering or scientific Notebook, such as pages, sections, and tabs.

The following sections describe the elements you might encounter as you interact with Notebooks. To see example Notebooks, browse through the Notebooks installed in the `Problem Solvers` folder. Refer to [Notebook Example: Expression Evaluator](#) later in this chapter for information about Problem Solvers and interacting with them.

Notebook Objects

Notebook developers can arrange information in a free-form manner on Notebook pages. Each piece of information that the developer places on a Notebook page is known as an *object*. As with a real notebook, many types of objects can be placed on a page, including text, numerics, and graphs.

You can interact with some objects on a Notebook page. For example, you can edit text in text objects, and you can rotate, zoom, and pan three-dimensional graphs. The Notebook developer also might include controls that allow you to modify the properties of an object. For example, they might include an option that allows you to select the plot style for a graph.

Scripts

The HiQ Notebook includes an object known as the HiQ-Script object. *HiQ-Script* is the built-in programming language that accesses the HiQ library of analysis and visualization functions.

In most Notebooks, you will see scripts in *Run View*. Run View is a special view of the script object that hides the script that performs the analysis or visualizes the data. Figure 2-1 shows the Expression Evaluator Notebook, which contains two scripts in Run View: **Evaluate** and **Clear**. When you press the run button (arrow) for the Evaluate script, the expression is plotted on the graph. When you press the run button for Clear, the plots are removed from the graph. If you receive a Notebook with a script that is not in Run View, right click on the script object and select **Run** to execute the script.




Figure 2-1. Expression Evaluator Problem Solving Scripts

Working with Multiple Windows

HiQ products use the standard Multiple Document Interface (MDI) that Microsoft Office products like Word and Excel use. A main window exists within which multiple HiQ Notebooks may reside. From the **Windows** menu, you can maximize, overlay, or tile the Notebook windows you open.

Interacting with a Notebook

A well designed Notebook should be self-documenting, describing how to interact with the Notebook. Interaction might be as simple as entering a start time and a stop time for simulation of a system of differential equations. Or a Notebook might instruct you to select a data file to import in order to calculate and graph the amount of rainfall in a particular area.

Most Notebooks include scripts that you can run to solve the type of mathematical or visualization problem the Notebook was designed to handle.

Notebook Example: Expression Evaluator

This section presents the Expression Evaluator Problem Solver to demonstrate how you can interact with HiQ Reader Notebooks. Problem Solvers are HiQ Notebooks designed to interact with users to analyze or solve a wide range of problems belonging to a certain class. In a Problem Solver, you can enter a different set of data or analysis problems without having to modify script.

Perform the following steps to learn more about the Expression Evaluator Notebook.

Opening the Notebook

1. Launch HiQ Reader from the Windows **Start** menu (**Start»Programs»National Instruments HiQ»HiQ Reader**).
2. Select **File»Open**.
3. Open the Problem Solvers folder within the HiQReader folder.
4. Select **Expression Evaluator.HiQ** and click **Open**. The Expression Evaluator Notebook opens.

Entering Data and Running Scripts

This Notebook can evaluate any mathematical expression and display its behavior graphically.

1. Click the **Evaluate** button to evaluate the expression. The Notebook evaluates the default expression over 128 points, starting at 1 and ending at 4. The graph displays the result.
2. Enter the mathematical expression $\sin(x) * \cos(x)$ into the text object labeled **F(x) =**.
3. Click the **Evaluate** button to evaluate the expression. Figure 2-2 shows the Expression Evaluator Problem Solver after it has evaluated two expressions.




Figure 2-2. Evaluating Expressions with the Expression Evaluator Notebook

4. Evaluate your own expression, varying the domain interval and number of points plotted to see how this Problem Solver behaves. You can press the **Clear** button to remove all plots.

The expression you entered is fed into the numerical algorithm in the script. The plot that appears when you run the script is a graphical representation of the mathematical expression that you entered.

**Note**

*You must use valid operators and valid HiQ built-in functions. In this example, your expression must be in terms of x . Refer to the HiQ Reader online help by selecting **Help»HiQ Reader Help Topics** for complete descriptions of operators and built-in functions.*

More Reader Notebooks: Problem Solvers

HiQ Reader comes with several other problem solvers that address various areas in science and engineering. Check the `\Problem Solvers` directory for Notebooks that solve the following types of problems:

- Filtering
- Windowing
- Data Fitting
- Optimization
- Root Finding
- Differential Equations
- Integration
- Nonlinear Systems



Technical Support Resources

National Instruments offers technical support through electronic, fax, and telephone systems. The electronic services include our Web site, an FTP site, and a fax-on-demand system. If you have a hardware or software problem, please first try the electronic support systems. If the information available on these systems does not answer your questions, contact one of our technical support centers, which are staffed by applications engineers, for support by telephone and fax. To comment on the documentation supplied with our products, send e-mail to techpubs@natinst.com.

Web Site

The InstrumentationWeb address is www.natinst.com.

From this Web site you can connect to our Web sites around the world (www.natinst.com/niglobal/) and access technical support (www.natinst.com/support/).

FTP Site

To access our FTP site, log in to our Internet host, [ftp.natinst.com](ftp://ftp.natinst.com), as `anonymous` and use your e-mail address, such as `yourname@anywhere.com`, as your password. The support files and documents are located in the `\support` directories.

Fax-on-Demand Support

Fax-on-Demand is a 24-hour information retrieval system containing a library of documents in English on a wide range of technical information. You can access Fax-on-Demand from a touch-tone telephone at 512 418 1111.

E-Mail Support

You can submit technical support questions to the applications engineering team through e-mail at support@natinst.com. Remember to include your name, address, and phone number so we can contact you with solutions and suggestions.

Telephone and Fax Support

National Instruments has branch offices all over the world. Use the following list to find the technical support number for your country. If there is no National Instruments office in your country, contact the source from which you purchased your software to obtain support.

Country	Telephone	Fax
Australia	03 9879 5166	03 9879 6277
Austria	0662 45 79 90 0	0662 45 79 90 19
Belgium	02 757 00 20	02 757 03 11
Brazil	011 284 5011	011 288 8528
Canada (Ontario)	905 785 0085	905 785 0086
Canada (Québec)	514 694 8521	514 694 4399
Denmark	45 76 26 00	45 76 26 02
Finland	09 725 725 11	09 725 725 55
France	0 1 48 14 24 24	0 1 48 14 24 14
Germany	089 741 31 30	089 714 60 35
Hong Kong	2645 3186	2686 8505
India	91805275406	91805275410
Israel	03 6120092	03 6120095
Italy	02 413091	02 4139215
Japan	03 5472 2970	03 5472 2977
Korea	02 596 7456	02 596 7455
Mexico (D.F.)	5 280 7625	5 520 3282
Mexico (Monterrey)	8 357 7695	8 365 8543
Netherlands	0348 433466	0348 430673
Norway	32 84 84 00	32 84 86 00
Singapore	2265886	2265887
Spain (Madrid)	91 640 0085	91 640 0533
Spain (Barcelona)	93 582 0251	93 582 4370
Sweden	08 587 895 00	08 730 43 70
Switzerland	056 200 51 51	056 200 51 55
Taiwan	02 2377 1200	02 2737 4644
United Kingdom	01635 523545	01635 523154
United States	512 795 8248	512 794 5678

Glossary

Prefix	Meanings	Value
p-	pico-	10^{-12}
n-	nano-	10^{-9}
μ -	micro-	10^{-6}
m-	milli-	10^{-3}
k-	kilo-	10^3
M-	mega-	10^6
G-	giga-	10^9
t-	tera-	10^{12}

A

ActiveX (Microsoft ActiveX) A programming system and user interface that lets you work with interactive objects. Formerly called OLE.

ActiveX control A standard software tool that adds additional functionality to any compatible ActiveX container.

B

built-in function One of many programming utilities in HiQ-Script that perform analysis, graphical, or utility operations.

C

compiled script A HiQ object containing HiQ-Script language that has been converted to code that a computer uses to execute the program.

ComponentWorks A collection of 32-bit ActiveX controls designed for building virtual instrumentation systems.

Glossary

E

error message	An information box that appears when HiQ cannot complete an action due to an internal error, compile error, run-time error, or user error.
Explorer	<i>See</i> HiQ Explorer.
expression	A mathematical operator and its operands.

H

HiQ Explorer	An interactive window displaying the objects, sections, and pages of an open Notebook.
HiQ extension	Extension for a HiQ base or professional version Notebook. Only Notebooks saved in HiQ Professional can be opened in HiQ Reader.
HiQ Professional	Professional version of HiQ, which includes the following elements: HiQ, HiQ Signal Processing Toolkit, ComponentWorks User Interface ActiveX controls, ComponentWorks DataSocket ActiveX control, ComponentWorks 3D Graph ActiveX control, Serial Interface ActiveX control, and HiQ Reader.
HiQ Reader	HiQ product that enables HiQ Professional users to distribute their Notebooks. HiQ Reader users can view and interact with Notebooks but cannot modify the format of the Notebook, create new objects, or create new notebooks.
HiQ-Script	The intuitive HiQ programming language for mathematics.
HQR extension	Extension for a HiQ Reader Notebook.

N

Notebook	The workspace in HiQ that stores, organizes, and displays all the components of an analysis and visualization problem.
----------	--

O

object	An entity in a HiQ Notebook that contains data of a specific type, for example, numeric, graphic, text, or HiQ-Script. Objects work together in a Notebook to generate and display solutions to analysis and visualization problems. Objects are always stored in a Notebook, but are not always visible on a Notebook page. <i>See</i> object view.
object view	A HiQ object that is visible on a Notebook page.
operand	An object (or objects) modified by an operator.
operator	Code in HiQ-Script that is specific to basic mathematical operations and structure of HiQ-Script language. Often represented as a symbol, for example, "/" represents division.

P

pop-up menu	A context-sensitive menu that you can access by right clicking with your mouse on an object or on the Notebook.
Problem Solver	A HiQ Notebook containing objects, including HiQ-Script, that allows you to interactively perform analysis of data and display results for a broad class of problems. For example, the Expression Evaluator Problem Solver can display the results of any expression.

R

Reader	<i>See</i> HiQ Reader.
Run View	View of the script object that displays 2 buttons—one to run the script and the other to stop the script—and hides the script source.

S

script	A block of code that performs a certain task. <i>See</i> HiQ-Script and compiled script.
script object	A HiQ object type containing HiQ-Script and from which you compile and execute your program.

Glossary

section tabs	An organizing tool in a HiQ Notebook that lets you label and quickly access different parts of your Notebook.
Standard toolbar	Site on the user interface of HiQ that contains basic utility tools, for example, Save , Open , Cut , Paste , and Print . Depending on your preference, the toolbar can appear on any edge of the interface, or as a floating window.
status bar	A region, usually the bottom of a window, containing information about HiQ and any selected object.

T

toolbar	Site on an application interface that contains various buttons and other controls. Depending on your preference, a toolbar can appear on any edge of the interface, or a floating window.
tooltip	A small, descriptive pop-up window that appears when you position the mouse cursor over a toolbar icon.



Artisan Technology Group is your source for quality new and certified-used/pre-owned equipment

- FAST SHIPPING AND DELIVERY
- TENS OF THOUSANDS OF IN-STOCK ITEMS
- EQUIPMENT DEMOS
- HUNDREDS OF MANUFACTURERS SUPPORTED
- LEASING/MONTHLY RENTALS
- ITAR CERTIFIED SECURE ASSET SOLUTIONS

SERVICE CENTER REPAIRS

Experienced engineers and technicians on staff at our full-service, in-house repair center

*InstraView*SM REMOTE INSPECTION

Remotely inspect equipment before purchasing with our interactive website at www.instraview.com ↗

WE BUY USED EQUIPMENT

Sell your excess, underutilized, and idle used equipment. We also offer credit for buy-backs and trade-ins. www.artisanng.com/WeBuyEquipment ↗

LOOKING FOR MORE INFORMATION?

Visit us on the web at www.artisanng.com ↗ for more information on price quotations, drivers, technical specifications, manuals, and documentation

Contact us: (888) 88-SOURCE | sales@artisanng.com | www.artisanng.com